

This guide outlines the procedure for changing label sets for an alignment, and it summarizes the alignment labels sets provided with the Minnesota drawing template.

Changing Label Sets for an Alignment

1. Select an alignment in the drawing
2. Right click and select *Edit Alignment Labels...* from the shortcut menu
3. In the *Alignment Labels* window, click on the *Import label set...* button.
4. Select a new alignment label set from the drop-down menu in the *Select Style Set* window.
5. Click on the *OK* button in the *Select Style Set* and the *Alignment Labels* windows.

Minnesota Drawing Template Alignment Label Sets


Label Set: _No Display
 Major Stations: None
 Minor Stations: None
 Geometry Labels: None
 Preview:



Label Set: Major(Par) Minor (100 and 50)
 Major Stations: Station labels placed parallel to the alignment line at 100 foot intervals
 Minor Stations: Ticks placed at 50 foot intervals
 Geometry Labels: None
 Preview:



Label Set: Major(Par) Minor (500 and 100)
Major Stations: Station labels placed parallel to the alignment line at 500 foot intervals
Minor Stations: Tics placed at 100 foot intervals
Geometry Labels: None
Preview:



Label Set: Major(Perp) Minor (100 and 50)
Major Stations: Station labels placed perpendicular to the alignment line at 100 foot intervals
Minor Stations: Tics placed at 50 foot intervals
Geometry Labels: None
Preview:



Label Set: Major(Perp) Minor (100 and 50) Geometry
 Major Stations: Station labels placed perpendicular to the alignment line at 100 foot intervals
 Minor Stations: Tics placed at 50 foot intervals
 Geometry Labels: Yes
 Preview:



Label Set: Major(Perp) Minor (500 and 100)
 Major Stations: Station labels placed perpendicular to the alignment line at 500 foot intervals
 Minor Stations: Tics placed at 100 foot intervals
 Geometry Labels: None
 Preview:



Label Set: Major(Perp) Minor (500 and 100) Geometry
Major Stations: Station labels placed perpendicular to the alignment line at 500 foot intervals
Minor Stations: Tics placed at 100 foot intervals
Geometry Labels: Yes
Preview:

